









## **GeoCoder Object** Reference Guide

## Copyright

Companies, names, and data used in examples herein are fictitious unless otherwise noted. No part of this document may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose, without the express written permission of Melissa Data Corporation. This document and the software it describes are furnished under a license agreement, and may be used or copied only in accordance with the terms of the license agreement.

© 2013. Melissa Data Corporation. All rights reserved.

Information in this document is subject to change without notice. Melissa Data Corporation assumes no responsibility or liability for any errors, omissions, or inaccuracies that may appear in this document.

## Trademarks

GeoCoder Object is a trademark of Melissa Data Corporation. Windows is a registered trademark of Microsoft Corp.

The following are registrations and trademarks of the United States Postal Service<sup>®</sup>: United States Postal Service, ZIP, ZIP Code, and ZIP + 4.

#### MELISSA DATA CORPORATION

22382 Avenida Empresa Rancho Santa Margarita, CA 92688-2112

Phone: 1-800-MELISSA (1-800-635-4772) Fax: 949-589-5211

E-mail: info@MelissaData.com Web site: www.MelissaData.com

For the latest version of this Reference Guide, visit http://www.MelissaData.com/tech/geocoder.htm.

Document Code: GCORFG Revision Number: 131216.242 Last Update: December 16, 2013

## Dear Programmer,

I would like to take this opportunity to thank you for your interest in Melissa Data products and introduce you to the company.

Melissa Data has been a leading provider of data quality and address management solutions since 1985. Our data quality software, Cloud services, and data integration components verify, standardize, consolidate, enhance and update U.S., Canadian, and global contact data, including addresses, phone numbers, and email addresses, for improved communications and ROI. More than 5,000 companies rely on Melissa Data to gain and maintain a single, accurate and trusted view of critical information assets

This manual will guide you through the functions of our easy-to-use programming tools. Your feedback is important to me, so please don't hesitate to email your comments or suggestions to me at: Ray@MelissaData.com.

I look forward to hearing from you.

Best Wishes,

Kay Mil-

Raymond F. Melissa President

# Table of Contents

Chapter 1: Introduction to GeoCoder Object Entering Your GeoCoder Object License Using GeoCoder Object.	
Chapter 2: GeoCoder Object Functions	
Initialize GeoCoder Object	
Geocoding ZIP Codes and Addresses	
Retrieve Results	
Retrieve Geocode Data	

# Chapter 1 Introduction to GeoCoder Object

GeoCoder Object retrieves the following information for a submitted 5-digit ZIP Code  ${}^{\rm TM}$  or 9-digit ZIP + 4  ${}^{\rm tR}$ :

- County name
- County FIPS code
- Census Block
- Census Tract
- Core Based Statistical Area (CBSA) information
- Time zone
- Latitude and longitude of the ZIP centroid

With a 6-digit Canadian Postal Code, GeoCoder Object will return:

- Time zone
- Latitude and longitude of the Postal Code centroid

For example, if you submitted the ZIP + 4 of "92688-2112," the GeoCoder Object would return:

Function	Value
GetCensusBlock	4021
GetCensusTract	03206
GetCountyFIPS	06059
GetCountyName	Orange
GetLatitude	33.638915
GetLongitude	-117.603858

GeoCoder Object is compatible with many of the most popular programming languages, including Access, Active Server Pages, C, C++, Delphi, FoxPro, Power Builder, and Visual Basic. For sample source code that you can utilize in your own applications, visit our website at **www.MelissaData.com**.

## **Geodetic System**

The GeoCoder Object uses WGS 84 standard, an Earth-centered, Earth-fixed terrestrial reference system and geodetic datum.

## **GeoPoint Coding**

Using multisource data, Melissa Data GeoPoint allows you to return latitude and longitude down to the rooftop of over 95% of all physical address in the United States. Within GeoPoint, there are two levels of accuracy: Rooftop and Interpolated Rooftop.

- Rooftop These are the most accurate latitude and longitude available with coverage of approximately 105 million individual addresses.
- Interpolated Rooftop These coordinates were computed using mathematical algorithms and street shape maps. While these coordinates are educated estimates, they should be quite accurate for the majority of the United States. There may be cases where the location of interpolated points is not very near the actual residence, mostly in rural areas with long streets and non-standard house numbering. However, these coordinates are still much more accurate than ZIP + 4 coordinates.

The basic version of GeoCoder Object lacks this GeoPoint feature. It is still accurate to the ZIP + 4 level.

## 1.1: Entering Your GeoCoder Object License

The license string is a software key that unlocks the functionality of the component. Without this key, the object does not function. You set the license string using an environment variable called MD\_LICENSE. If you are just trying out GeoCoder Object and have a demo license, you can use the environment variable MD\_LICENSE\_DEMO for this purpose. This avoids conficts or confusion if you already have active subscriptions to other Melissa Data object products.

In earlier versions of GeoCoder Object, you would set this value with a call to the **SetLicenseString** function. Using an environment variable makes it much easier to update the license string without having to edit and re-compile the application.

It used to be necessary, even when employing an environment variable, to call the **SetLicenseString** function without passing the license string value. This is longer true. GeoCoder Object will still recognize the **SetLicenseString** function, but you should eventually remove any reference to it from your code.

#### Windows

Windows users can set environment variables by doing the following:

- 1 Select Start > Settings, and then click Control Panel.
- 2 Double-click System, and then click the Advanced tab.
- **3** Click **Environment Variables**, and then select either *System Variables* or *Variables for the user X*.
- 4 Click New.
- 5 Enter "MD\_LICENSE" in the Variable Name box.
- 6 Enter the license string in the Variable Value box, and then click OK.

Please remember that these settings take effect only upon start of the program. It may be necessary to quit and restart the application to incorporate the changes.

#### Linux/Solaris/HP-UX/AIX

Unix-based OS users can simply set the license string via the following (use the actual license string, instead):

export MD\_LICENSE=A1B2C3D4E5

If this setting is placed in the .profile, remember to restart the shell.

GeoCoder Object also used to employ its own environment variable, MDGEO\_LICENSE. The MD\_LICENSE variable is shared across the entire Melissa Data product line of programming tools. GeoCoder Object will still use the old license variable for the time being, but you should transition to using MD\_LICENSE as soon as possible.

## 1.2: Using GeoCoder Object

1 Create an instance of GeoCoder Object.

Create GeoCoder as New Instance of mdGeo

2 Set the path to the data files.

CALL SetPathToGeoCodeDataFiles WITH DataPath

3 Call the InitializeDataFiles function to connect the GeoCoder Object to its supporting data file.

```
CALL InitializeDataFiles RETURNING Result
IF Result <> 0 Then
CALL GetInitializeErrorString RETURNING ErrorString
PRINT "Error: " & ErrorString
ENDIF
```

4 To geocode a ZIP Code, call the **ComputeDistance** function, passing the ZIP Code to be coded as a parameter. If this function returns a false or zero value, check the **GetResults** function for the cause of the failure.

```
CALL ComputeDistance WITH Zip5, Plus4
CALL GetResults RETURNING ResultCode
IF ResultCode CONTAINS "GS01", "GS02", "GS03", "GS05", OR
      "GS06" THEN
   CALL GetCountyName RETURNING CountyName
   CALL GetCountyFips RETURNING CountyFIPSCode
   CALL GetCensusBlock RETURNING CensusBlock
   CALL GetCensusTract RETURNING CensusTract
   CALL GetLatitude RETURNING Latitude
   CALL GetLongitude RETURNING Longitude
   CALL GetPlaceCode RETURNING PlaceCode
   CALL GetPlaceName RETURNING PlaceName
   CALL GetCBSACode RETURNING CBSACode
   CALL GetCBSALevel RETURNING CBSALevel
   CALL GetCBSATitle RETURNING CBSATitle
   CALL GetCBSADivisionCode RETURNING CBSADivisionCode
   CALL GetCBSADivisionLevel RETURNING CBSADivisionLevel
   CALL GetCBSADivisionTitle RETURNING CBSADivisionTitle
   CALL GetTimeZone RETURNING TimeZone
   CALL GetTimeZoneCode RETURNING TimeZoneCode
ELSE
   PRINT ResultCode
ENDIF
```

## **GeoPoint Sample**

The procedure for returning the optional doorstop-level GeoPoint data is almost identical to the GeoCode procedure, assuming you have purchased a GeoPoint license, with the following exceptions.

1 You must also set the path to the GeoPoint data files before calling the **GetInitializeErrorString** function.

CALL SetPathToGeoCodeDataFiles WITH GeoCodeDataPath CALL SetPathToGeoPointDataFiles WITH GeoPointDataPath

2 Call the GeoPoint function instead of the ComputeDistance function. This function has one extra parameter, which is the Delivery Point Code for a specific address.

```
CALL GeoPoint WITH Zip5, Plus4, DPC RETURNING Result
CALL GetResults RETURNING ResultCode
IF ResultCode CONTAINS "GS01", "GS02", "GS03", "GS05", OR
"GS06" THEN
Process Return Data Identically to Geocode
ELSE
PRINT ResultCode
ENDIF
```

## **Recent Changes to GeoCoder Object**

#### July 20, 2011

Canadian GeoCoding was added.

#### October 28, 2010

The GeoPoint option has been upgraded to include interpolated locations. See page 2 in this chapter for more information about interpolation.

#### December 11, 2009

The GetStatus Code and GetErrorCode functions are being deprecated in favor of the GetResults function. This function returns a comma delimited string of codes that combine the information in the two deprecated functions. See Section 2.1.3, *Retrieve Results*, on page 24 for more information.

# Chapter 2 GeoCoder Object Functions

## 2.1: GeoCoder Function List

## 2.1.1: Initialize GeoCoder Object

These functions initialize GeoCoder Object and connect it to its data files.

SetPathToGeoCodeDataFiles	9
SetPathToGeoPointDataFiles	10
SetPathToGeoCanadaDataFiles	11
SetLicenseString	11
InitializeDataFiles	12
Initialize (Deprecated)	13
GetInitializeErrorString	15
GetBuildNumber	15
GetDatabaseDate	16
GetExpirationDate	16
GetLicenseExpirationDate	17

## 2.1.2: Geocoding ZIP Codes and Addresses

These function retrieve the geographic data for a given ZIP Code (ComputeDistance function) or address (GeoPoint function).

ComputeBearing	
ComputeDistance	
GeoCode	20
GeoPoint	21

## 2.1.3: Retrieve Results

The following functions return information on the success of the last call to either to the ComputeDistance or GeoPoint function. GetStatusCode and GetErrorCode are considered deprecated.

## 2.1.4: Retrieve Geocode Data

The following functions return the geo information from the last call to either the ComputeDistance or GeoPoint function.

GetCBSACode	29
GetCBSALevel	
GetCBSATitle	
GetCBSADivisionCode	
	-
GetCBSADivisionLevel	-
GetCBSADivisionTitle	-
GetCensusBlock	-
GetCensusTract	
GetCountyFips	34
GetCountyName	35
GetLatitude	
GetLongitude	
GetPlaceCode	
GetPlaceName	
GetTimeZone	
GetTimeZoneCode	

## 2.1.1: Initialize GeoCoder Object

These functions initialize GeoCoder Object and connect it to its data files.

## **SetPathToGeoCodeDataFiles**

This function passes a string value containing the path to the data files used by GeoCoder Object.

## Remarks

This function must be called prior to calling the **InitializeDataFiles** function. The value must contain a valid path to the directory that contains the GeoCode data files, mdGeo.dat and mdGeo.lic.

## **Syntax**

object->SetPathToGeoCodeDataFiles(StringValue);

С

mdEmailSetPathToGeoCodeDataFiles(object, \*char);

#### COM

object.PathToGeoCodeDataFiles = StringValue

## SetPathToGeoPointDataFiles

This function passes a string value containing the path to the data files used by the **GeoPoint** function of GeoCoder Object.

## Remarks

This function must be called prior to calling the **InitializeDataFiles** function. It is optional if you do not intend to use the **GeoPoint** function.

The value must contain a valid path to the directory that contains the GeoPoint data files, mdGeoPoint.idx and mdGeoPoint.dat.

## **Syntax**

```
object->SetPathToGeoPointDataFiles(StringValue);
```

С

mdEmailSetPathToGeoPointDataFiles(object, \*char);

#### СОМ

object.PathToGeoPointDataFiles = StringValue

## SetPathToGeoCanadaDataFiles

This function passes a string value containing the path to the data files used by the **ComputeDistance** and **GeoPoint** function to geocode Canadian postal codes.

## Remarks

This function must be called prior to calling the **InitializeDataFiles** function. It is optional if you do not intend to geocode Canadian addresses.

The value must contain a valid path to the directory that contains the Canadian geocoing data file: mdGeoCanada.db.

## **Syntax**

```
object->SetPathToGeoCanadaDataFiles(StringValue);
```

С

mdEmailSetPathToGeoCanadaDataFiles(object, \*char);

#### СОМ

object.PathToGeoCanadaDataFiles = StringValue

## SetLicenseString

The License String is a software key from Melissa Data that unlocks the full functionality of the component.

## Remarks

The license string is used to unlock a component's full functionality. The license string is included with the documentation you received.

If you have not purchased a license, call Melissa Data toll free at 1-800-MELISSA (1-800-635-4772) or send an email to sales@MelissaData.com.

The license string is normally set using an environment variable, either MD\_LICENSE or MD\_LICENSE\_DEMO. Calling **SetLicenseString** is an alternative method for setting the license string, but applications developed for a production environment should only use the environment variable.

When using an environment variable, it is not necessary to call the **SetLicenseString** function.

For more information on setting the environment variable, see page 3 of this guide.

If the license string is not set, the component will operate in a demonstration mode (limited to Nevada ZIP Codes) and will return the string "DEMO" after the **GetBuildNumber** function.

#### Input Parameters

The SetLicenseString function has one parameter.

**LicenseString** A string value representing the license.

If the license string is already set as an environment variable, only an the input parameter is passed as an empty string.

#### **Return Value**

The **SetLicenseString** function returns a Boolean value of 0 (FALSE) or 1 (TRUE). It will return a FALSE Boolean value if the license string provided is incorrect.

```
Syntax
COM
BooleanValue = object.SetLicenseString(LicenseString)
C++
BooleanValue = object->SetLicenseString(LicenseString);
C
IntegerValue = mdGeoSetLicenseString(object, LicenseString);
```

## **InitializeDataFiles**

The **InitializeDataFiles** function opens the required data files and prepares the GeoCoder Object for use.

## Remarks

The **SetPathToGeoCodeDataFiles** function must be called prior to calling this function. If you wish to use the optional **GeoPoint** function for greater accuracy, the **SetPathToGeoPointDataFiles** function must also be called.

If this function returns any value other than No Error, call the **GetInitializeErrorString** function to determine the cause of the failure.

The GeoCoder Object data expires nine months after the date indicated by the **GetDatabaseDate** function. After this date, a "DataFile Expired" error is returned.

#### **Return Value**

The **InitializeDataFiles** function returns an integer value of 0 if successful, and a non-zero value if unsuccessful.

Return Value	Initialize Error String	Return Value	Initialize Error String
0	No error.	2	Insufficient memory to initialize.
-1	Not initialized.	3	County file error.
1	Invalid path to data.	4	Data File Expired.

## **Syntax**

```
IntegerValue = object->InitializeDataFiles();
```

С

```
IntegerValue = mdGeoInitializeDataFiles(object);
```

СОМ

IntegerValue = object.InitializeDataFiles()

## Initialize (Deprecated)

This function has been deprecated in favor of the InitializeDataFiles function. It may still be called instead of the InitializeDataFiles function if the GeoPoint functionality is not being used, but calling the InitializeDataFiles function is now the preferred method and required for using the GeoPoint function.

This function opens the required data files and prepares the GeoCoder Object for use.

## Remarks

if this function returns any value other than 0, call the **GetInitializeErrorString** function to determine the cause of the failure.

GeoCoder data expires nine months after the GeoCoder Object database date. After this date, a "DataFile Expired" error is returned.

#### **Input Parameters**

The **Initialize** function has the following optional parameters:

DataPath	A string containing the path to the mdGeo.dat and mdGeo.lic file locations.
	The path parameter is optional. If the path is not given, the Initialize function will look for this data file in the same directory as the GeoObj.dll file (for Windows) or the target directory (for Unix).
IndexPath	A string containing the path to the mdGeo.idx and mdGeo.cty file locations.
	The path parameter is optional. If the path is not given, the Initialize function will look for this data file in the same directory as the GeoObj.dll file (for Windows) or the target directory (for Unix).

#### **Return Value**

The **Initialize** function returns the same values as the **InitializeDataFiles** function, show in the table on page 13.

### **Syntax**

IntegerValue = object->Initialize(DataPath, IndexPath);

С

IntegerValue = mdGeoInitialize(object, DataPath, IndexPath);

#### СОМ

IntegerValue = object.Initialize(DataPath, IndexPath)

## GetInitializeErrorString

This function returns a descriptive string to describe any error in a call to the **InitializeDataFiles** function.

## Remarks

If called before the **InitializeDataFiles** function, this function will return an empty string.

```
Syntax
```

```
StringValue = object->GetInitializeErrorString();
```

С

StringValue = mdGeoGetInitializeErrorString(object)

COM

StringValue = object.GetInitializeErrorString

## GetBuildNumber

The **GetBuildNumber** function returns the current development release build number of GeoCoder Object.

## Remarks

The word "DEMO" will be returned after the build number if no license string is provided, or if an incorrect license string is entered.

```
Syntax
```

```
StringValue = object->GetBuildNumber();
```

#### С

StringValue = mdGeoGetBuildNumber(object);

#### СОМ

StringValue = object.GetBuildNumber()

## GetDatabaseDate

The **GetDatabaseDate** function returns a date value representing the date of the GeoCoder Object database. GeoCoder data expires nine months after the GeoCoder Object database date.

## Remarks

If the **GetDatabaseDate** function is called before the **InitializeDataFiles** function is called and the data files are not in the installation directory, the object will return a value of "12/30/1899".

#### **Return Value**

The **GetDatabaseDate** function returns a value representing the date of the GeoCoder Object database. The COM object returns a date value, while the standard object returns a string value.

## **Syntax**

StringValue = object->GetDatabaseDate();

С

StringValue = mdGeoGetDatabaseDate(object);

#### СОМ

DateTime = object.GetDatabaseDate()

## GetExpirationDate

The **GetExpirationDate** function returns a date value representing the date your data files expire. This date allows you to confirm that the data files you are using are the latest ones.

## Remarks

If the **GetExpirationDate** function is called before the **InitializeDataFiles** function is called, an exception will be reported.

#### **Return Value**

The **GetExpirationDate** function returns a value representing the expiration date of the data files. The COM object returns a date value, while the standard object returns a string value.

## **Syntax**

```
StringValue = object->GetExpirationDate();
C
StringValue = mdGeoGetExpirationDate(object);
COM
DateTime = object.GetExpirationDate()
```

## **GetLicenseExpirationDate**

Returns a string value containing the expiration date of the current license string.

## Remarks

Call this function to determine when your current license will expire. After this date, GeoCoder Object will no longer function.

## **Syntax**

```
StringValue = object->GetLicenseExpirationDate()
```

С

StringValue = mdGeoGetLicenseExpirationDate(object)

#### СОМ

StringValue = object.GetLicenseExpirationDate

## 2.1.2: Geocoding ZIP Codes and Addresses

These function retrieve the geographic data for a given ZIP Code (**ComputeDistance** function) or address (**GeoPoint** function).

## ComputeBearing

The ComputeBearing Method returns a bearing of 0 to 360 degrees representing the compass direction from point 1 to point 2. To convert your bearing to an approximate compass direction, use the following table:

Direction	Degrees	Direction	Degrees
Ν	0 to 22.5, 337.5 to 0	S	157.5 to 202.5
NE	22.5 to 67.5	SW	202.5 to 247.5
Е	67.5 to 112.5	W	247.5 to 292.5
SE	112.5 to 157.5	NW	292.5 to 337.5

## Remarks

If an invalid latitude or longitude is entered, a value of 999 will be returned.

You do not have to call the **Initialize (Deprecated)** function before calling the **ComputeBearing** function.

#### **Input Parameters**

The method accepts four double-precision floating point numbers.

- lat1 latitude for point 1 [In Degrees (90 to -90)]
- long1 longitude for point 1 [In Degrees (180 to -180)]
- lat2 latitude for point 2 [In Degrees (90 to -90)]
- long2 longitude for point 2 [In Degrees (180 to -180)]

#### **Return Value**

The ComputeBearing Method returns a double-precision bearing based on input latitudes & longitudes.

## **Syntax**

```
Double = object.ComputeBearing (lat1, long1, lat2, long2)
```

## ComputeDistance

The ComputeDistance Method returns a distance in miles between point 1 and point 2.

## Remarks

If an invalid latitude or longitude is entered, a value of 999 will be returned.

You do not have to call the **Initialize (Deprecated)** function before calling the **ComputeDistance** function.

#### **Input Parameters**

The method accepts four double-precision floating point numbers.

- lat1 latitude for point 1 [In Degrees (90 to -90)]
- long1 longitude for point 1 [In Degrees (180 to -180)]
- lat2 latitude for point 2 [In Degrees (90 to -90)]
- long2 longitude for point 2 [In Degrees (180 to -180)]

#### **Return Value**

The ComputeDistance Method returns the distance in miles between two points based on the input latitudes & longitudes.

## GeoCode

This function obtains and sets the return values of the GeoCoder Object with Geographic and Census data, using an input ZIP Code and Plus4.

## Remarks

If a 9-digit ZIP Code or 5-digit ZIP Code and Plus4 are used as parameters for the **GeoCode** function, the following will be done in order, if the previous fails:

- 1 Information will be obtained from the full ZIP and Plus4 combination. The **GetResults** function will return "GS01."
- 2 If no information is found for the Plus4, the centroid for the ZIP+2 segment will be used (The ZIP Code & first two digits of the Plus4). The **GetResults** function will return "GS02."
- 3 If the ZIP+2 segment cannot be found, the centroid for the 5-digit ZIP Code will be used. The **GetResults** function will return "GS03."

#### Input Parameters

The GeoCode function has the following parameters:

**Zip (Required)** The 5-digit ZIP Code, 9-digit ZIP + 4 code, or 6-digit Canadian Postal Code. A ZIP Code can consist of five digits to represent a 5-digit ZIP Code, or nine digits to represent a ZIP + 4 code. If the ZIP + 4ZIP + 4 is included here, a hyphen can be used to separate the two numbers, but is not required.

Plus4 (Optional) The 4-digit Plus4 code if not included with the ZIP parameter.

When geocoding Canadian postal codes the full six-digit postal code must be included in the first parameter (Zip),

#### **Return Value**

The GeoCode function returns a Boolean value of 0 (FALSE) or 1 (TRUE).

A TRUE return will set the return values of the various functions described in the section beginning on page 29. On a FALSE return, check the **GetResults** function.

#### **Syntax**

С

```
Boolean = object->GeoCode("92688", "2112");
```

```
Integer = mdGeoGeoCode(object, "92688", "2112");
```

#### СОМ

```
Boolean = object.GeoCode("92688", "2112")
```

## GeoPoint

Obtains and sets the return values of the GeoCoder Object with Geographic and Census data, using an input ZIP Code, Plus4 and delivery point code. If successful, the data will be accurate to the rooftop level, rather than just the ZIP + 4 code, as with the **ComputeDistance** function.

## Remarks

If a five-digit ZIP Code, Plus4 and valid delivery point are used as parameters for the **GeoPoint** function, the following will be done in order, if the previous fails:

1 Rooftop-level information will be obtained for the full combination of ZIP Code, Plus4 and Delivery Point Code (Result Code "GS05").

- 2 If the Delivery Point Code is not found, information will be returned for the centroid of the ZIP and Plus4 combination (Result Code "GS01").
- 3 If no information is found for the Plus4, the centroid for the ZIP+2 (The ZIP Code & first two digits of the Plus4) segment will be used (Result Code "GS02").
- 4 If the ZIP+2 segment cannot be found, the centroid for the 5-digit ZIP Code will be used (Result Code "GS03")
- 5 Check the return value of the **GetResults** function to verify the level to which the record was coded.

#### Input Parameters

The **GeoPoint** function can use one of the two following sets of string values as parameters:

AddressKey	This is the preferred input. The 11-digit AddressKey contains all the information that the object requires. If the AddressKey input is used, do not use the other input parameters.
Or:	
Zip	The 5-digit ZIP Code, 9-digit ZIP + 4 code, or 6-digit Canadian Postal Code. A ZIP Code can consist of five digits to represent a 5-digit ZIP Code, or nine digits to represent a ZIP + 4 code. If the ZIP + 4 is included here, a hyphen can be used to separate the two numbers, but is not required.
Plus4	The four-digit Plus4 code.
DeliveryPoint Code	The two-digit Delivery Point Code.

The AddressKey parameter is the preferred input. However either the AddressKey or the combination of Zip, Plus4, and DeliveryPoint Code are valid. For Canadian records, the Plus4 and DeliveryPoint Code parameters must be blank.

Refer to the syntax below for an example usage of both inputs.

#### **Return Value**

The GeoPoint function returns a Boolean value of 0 (FALSE) or 1 (TRUE).

A TRUE return will set the return values of the functions described in the section beginning on page 29. On a FALSE return, check the **GetResults** function.

```
Syntax
Boolean = object->GeoPoint(AddressKey, "", "");
Boolean = object->GeoPoint(ZipCode, Plus4, DPC);
C
Integer = mdGeoGeoPoint(object, AddressKey, "", "");
Integer = mdGeoGeoPoint(object, ZipCode, Plus4, DPC);
COM
Boolean = object.GeoPoint(AddressKey, "", "")
Boolean = object.GeoPoint(ZipCode, Plus4, DPC)
```

## 2.1.3: Retrieve Results

The following functions return information on the success of the last call to either to the **ComputeDistance** or **GeoPoint** function. **GetStatusCode** and **GetErrorCode** are considered deprecated.

## GetResults

This function returns a string value containing status and error codes for the current record. Multiple codes are separated by commas.

## Remarks

The **GetResults** function may return one or more four-character strings, separated by commas, depending on the result generated by the current record.

The possible values are:

Code	Short Desc.	Long Description
GS01	Geocoded to Street Level	The record was geocoded to the street (thoroughfare) level (Zip+4 for US, full postal code for CA).
GS02	Geocoded to Neighborhood Level	The record was geocoded to the neighborhood level (Zip+2 for US).
GS03	Geocoded to City Level	The record was geocoded to the city (locality) level (ZIP centroid for US, 3-digit postal code for CA).
GS05	Geocoded to Rooftop Level	The record was geocoded to the rooftop level.
GS06	Geocoded to Interpolated Rooftop Level <sup>*</sup>	The record was geocoded to the rooftop level using interpolation (educated estimations using street coordinates).
GE01	Invalid Postal Code	The submitted postal code is not in a valid format.
GE02	Postal Code Not Found	The submitted postal code was not found in the database.
GE03	Demo Mode	Geocoder is in Demo mode and a zip code outside the Demo range was detected.
GE04	Data Files Expired	Geocoder data files are expired. Please update with the latest data files.

\* See *GeoPoint Coding* on page 2 for more information on interpolated rooftop coding.

If the location information in the current record was valid, this field will contain the value "GS01" at the very minimum and may include more of the "GS" codes. If the address could not be verified, the codes beginning with "GE" will indicate the reason or reasons why verification failed.

## Syntax

```
char = object->GetResults()
C
char = mdGeoGetResults(object)
COM
string = object.Results
```

## GetResultCodeDescription

This function returns the description of the inputted Result Code. It can only be used through the Standard DLL.

It requires two values to be passed in, a Result Code and an enumerated option. If a string of Result Codes are inputted, only the first code will be used. The enumerated option will determine whether a short or long description will be returned.

Enumerated Value	Integer Value	Description
ResultCodeDescriptionLong	0	Returns a detailed description of the inputted result code.
ResultCodeDescriptionShort	1	Returns a brief description of the inputted result code.

## **Syntax**

```
StringValue = object->GetResultCodeDescription
(StringValue ResultCode,ResultCdDescOpt);
```

С

```
StringValue = mdGeoGetResultCodeDescription
(object,StringValue_ResultCode,int);
```

## GetStatusCode (Deprecated)

The Status Code indicates how precisely the **ComputeDistance** or **GeoPoint** information was matched after a successful call to either of those functions.

This function has been deprecated. You should use the **GetResults** function instead. See page 24 for documentation on this function.

## Remarks

The **GetStatusCode** function returns a one-character string value after a call to the **ComputeDistance** or **GeoPoint** function.

Possible return values from the GetStatusCode function are as follows:

Status Code	Explanation
В	Record was coded to rooftop level.
А	Record was coded to interpolated rooftop level.*
9	Record was coded to the ZIP + 4 centroid (U.S.) or or the full 6-digit Postal Code level (Canada).
7	Record was coded to the ZIP + 2 centroid.
5	Record was coded to the 5-digit ZIP Code centroid (U.S.) or or the first 3- digit Postal Code level (Canada).
Х	Record was not coded.
D	This object is in "Demonstration" mode and it detected the input of a ZIP Code outside the allowable range.
E	Expired.
* 0	

\* See *GeoPoint Coding* on page 2 for more information on interpolated rooftop coding. If neither the **ComputeDistance** function nor the **GeoPoint** function have not been called, this function will return an empty string.

## **Syntax**

```
StringValue = object->GetStatusCode();
C
StringValue = mdGeoGetStatusCode(object);
COM
StringValue = object.StatusCode
```

## GetErrorCode (Deprecated)

This function returns error code triggered by an unsuccessful call to the **ComputeDistance** or **GeoPoint** function.

This function has been deprecated. You should use the **GetResults** function instead. See page 24 for documentation on this function.

## Remarks

This function returns s a 1-character string value after an unsuccessful call to the **ComputeDistance** or **GeoPoint** function.

Possible return values from the GetErrorCode function are as follows:

Error Code	Reason for Error
Ν	Record Not Found — Unable to locate the ZIP Code.
Z	Bad ZIP Code (an invalid ZIP Code was entered, for example, "abcde")

If neither the **ComputeDistance** nor the **GeoPoint** function have been called, or if the function call did not result in an error, the return value of this function will be an empty string.

## **Syntax**

```
StringValue = object->GetErrorCode();
C
StringValue = mdGeoGetErrorCode(object);
COM
StringValue = object.ErrorCode
```

## 2.1.4: Retrieve Geocode Data

The following functions return the geo information from the last call to either the **ComputeDistance** or **GeoPoint** function.

## GetCBSACode

This function returns the five-digit code for the Core Based Statistical Area (CBSA).

## Remarks

Metropolitan and micropolitan statistical areas (metro and micro areas) are geographic entities defined by the U.S. Office of Management and Budget (OMB) for use by Federal statistical agencies in collecting, tabulating, and publishing Federal statistics. The term "Core Based Statistical Area" (CBSA) is a collective term for both metro and micro areas. A metro area contains a core urban area of 50,000 or more population, and a micro area contains an urban core of at least 10,000 (but less than 50,000) population. Each metro or micro area consists of one or more counties and includes the counties containing the core urban area, as well as any adjacent counties that have a high degree of social and economic integration (as measured by commuting to work) with the urban core.

The CBSA Code is a five-digit code for the specific CBSA associated with the location described by the submitted ZIP Code.

## **Syntax**

```
StringValue = object->GetCBSACode();
```

С

StringValue = mdGeoGetCBSACode(object);

#### СОМ

StringValue = object.CBSACode

## GetCBSALevel

This function returns the level description for the Core Based Statistical Area (CBSA), metropolitan or micropolitan.

## Remarks

For more information on Core Based Statistical Areas, see the **GetCBSACode** function on page 29.

# Syntax StringValue = object->GetCBSALevel(); C StringValue = mdGeoGetCBSALevel(object); COM StringValue = object.CBSALevel

## GetCBSATitle

Returns the official U.S. Census Bureau name for the Core Based Statistical Area (CBSA).

## Remarks

For more information on Core Based Statistical Areas, see the **GetCBSACode** function on page 29.

## Syntax

```
StringValue = object->GetCBSATitle();
```

#### С

```
StringValue = mdGeoGetCBSATitle(object);
```

#### СОМ

StringValue = object.CBSATitle

## GetCBSADivisionCode

This function returns the numeric code for the division within the Core Based Statistical Area containing the submitted ZIP Code.

## Remarks

Some CBSA's are broken into parts known as divisions. In this case, the CBSA Division functions will also be populated. If not, these fields will be empty. Each division also has a Code, Level and Title.

```
Syntax
```

С

```
StringValue = object->GetCBSADivisionCode();
```

StringValue = mdGeoGetCBSADivisionCode(object);

СОМ

StringValue = object.CBSADivisionCode

## GetCBSADivisionLevel

This function returns the level description (metropolitan or micropolitan) for the division within the Core Based Statistical Area containing the submitted ZIP Code.

## Remarks

Some CBSA's are broken into parts known as divisions. In this case, the return values of the CBSA Division functions will also be populated. If not, these values will be empty. Each division also has a Code, Level and Title.

## Syntax

```
StringValue = object->GetCBSADivisionLevel();
```

С

StringValue = mdGeoGetCBSADivisionLevel(object);

#### COM

```
StringValue = object.CBSADivisionLevel
```

# GetCBSADivisionTitle

This function returns the official U.S. Census Bureau's official name for the division within the Core Based Statistical Area containing the submitted ZIP Code.

#### Remarks

Some CBSA's are broken into parts known as divisions. In this case, the CBSA Division functions will also be populated. If not, these fields will be empty. Each division also has a Code, Level and Title.

```
Syntax
    char = object->GetCBSADivisionTitle();
C
    char = mdGeoGetCBSADivisionTitle(object);
COM
    string = object.CBSADivisionTitle
```

# GetCensusBlock

This function returns the Census Block number for the submitted ZIP + 4, returned after a successful call to the **ComputeDistance** or **GeoPoint** function.

## Remarks

Census blocks, the smallest geographic area for which the Bureau of the Census collects and tabulates decennial census data, are formed by streets, roads, railroads, streams and other bodies of water, other visible physical and cultural features, and the legal boundaries shown on Census Bureau maps.

A Census Block Group is a cluster of blocks having the same first digit of their 3-digit identifying numbers within a Census Tract or Block Numbering Area (BNA). For example, Census Block Group 3 within a Census Tractor BNA includes all blocks numbered between 301 and 397. In most cases, the numbering involves substantially fewer than 97 blocks. Census Block Groups never cross Census Tract or BNA boundaries, however, they may cross the boundaries of county subdivisions, places, American Indian and Alaskan Native areas, urbanized areas, voting districts, and congressional districts. Census Block Groups generally contain between 250 and 550 housing units, with the ideal size being 400 housing units.

Census Blocks are small areas bordered on all sides by visible features such as streets, roads, streams, and railroad tracks, and by invisible boundaries such as city, town, township, county limits, property lines, and short, imaginary extensions of streets and roads.

The **GetCensusBlock** function returns a 4-character string value after a call to the **ComputeDistance** or **GeoPoint** function. The first digit is the Block Group and the last three characters (if any) are the Block Number.

#### Example:

"103A" (Block Group is 1 & Block Number is 3A)

If neither the **ComputeDistance** nor the **GeoPoint** function have been called, or if the function call resulted in an error, this function value will be empty.

```
Syntax
```

```
char = object->GetCensusBlock();
C
char = mdGeoGetCensusBlock(object);
COM
string = object.CensusBlock
```

# GetCensusTract

This function returns the Census Tract number for the submitted location, returned after a successful call to the **ComputeDistance** or **GeoPoint** function.

## Remarks

Census Tracts are small, relatively permanent statistical subdivisions of a county. Census Tracts are delineated for all metropolitan areas (MA's) and other densely populated counties by local census statistical areas committees following Census Bureau guidelines (more than 3,000 Census Tracts have been established in 221 counties outside MA's).

The **GetCensusTract** function returns a four or six-character string value after a successful call to either the **ComputeDistance** or the **GeoPoint** function.

The Census Tract is usually returned as a 4-digit number. However, in areas that experience substantial growth, a Census Tract may be split to keep the population level even. When this happens, a 6-digit number will be returned.

If neither the **ComputeDistance** nor the **GeoPoint** function has been called, or if the function call resulted in an error, this value will be an empty string.

```
Syntax
    char = object->GetCensusTract();
C
    char = mdGeoGetCensusTract(object);
COM
    string = object.CensusTract
```

# GetCountyFips

This function returns the County FIPS code for the submitted ZIP Code, after a successful call to either the **ComputeDistance** or the **GeoPoint** function.

#### Remarks

The Federal Information Processing Standard (FIPS) is a 5-digit code defined by the U.S. Bureau of Census. The first two digits are a state code and the last three indicate the county within the state.

The **GetCountyFips** function returns a 5-character string value set by a call to the **ComputeDistance** or **GeoPoint** function. It is accurate to the 9-digit level.

#### Example:

"06037" is the County FIPS for Los Angeles, CA.

In the example above, "06" is the state code for California and "037" is the county code for Los Angeles.

If neither the **ComputeDistance** nor the **GeoPoint** function has been called, or if the function call resulted in an error, this value will be an empty string.

```
Syntax
```

```
StringValue = object->GetCountyFips();
```

```
StringValue = mdGeoGetCountyFips(object);
```

```
СОМ
```

С

```
StringValue = object.CountyFips
```

# GetCountyName

This function returns the County name for the submitted ZIP Code after a successful call to either the **ComputeDistance** or the **GeoPoint** function.

## Remarks

The **GetCountyName** function returns a 25-character (maximum) string after a successful call to either the **ComputeDistance** or the **GeoPoint** function.

If neither the **ComputeDistance** nor the **GeoPoint** function has been called, or if the function call resulted in an error, this value will be an empty string.

#### **Syntax**

```
StringValue = object->GetCountyName();
```

#### С

```
StringValue = mdGeoGetCountyName(object);
```

#### СОМ

```
StringValue = object.CountyName
```

# GetLatitude

This function returns the latitude for the submitted location after a successful call to either the **ComputeDistance** or the **GeoPoint** function.

## Remarks

Latitude is the geographic coordinate of a point measured in degrees north or south of the equator. The GeoCoder Object uses the WGS-84 standard for determining latitude.

The **GetLatitude** function returns a character string representing a numeric value, set by a call to either the **ComputeDistance** or the **GeoPoint** function.

Since all U.S. ZIP Code latitude coordinates are north of the equator, this value will always be positive.

If neither the **ComputeDistance** nor the **GeoPoint** function has been called, or if the function call resulted in an error, this function will return "0.0."

```
Syntax
StringValue = object->GetLatitude();
C
StringValue = mdGeoGetLatitude(object);
COM
StringValue = object.Latitude
```

# GetLongitude

This function returns the longitude of the submitted location after a successful call to either the **ComputeDistance** or the **GeoPoint** function.

#### Remarks

Longitude is the geographic coordinate of a point measured in degrees east or west of the Greenwich meridian. The GeoCoder Object uses the WGS-84 standard for determining longitude.

The **GetLongitude** function returns an 11-character string value set by a call to either the **ComputeDistance** or the **GeoPoint** function. Its negative number indicates a point west of the Greenwich meridian.

If neither the **ComputeDistance** nor the **GeoPoint** function has been called, or if the function call resulted in an error, this function will return "0.0."

#### **Syntax**

```
StringValue = object->GetLongitude();
```

```
C
StringValue = mdGetGetLongitude(object);
```

#### СОМ

StringValue = object.Longitude

# GetPlaceCode

This function returns the Census Bureau place code associated with the location passed to either the **ComputeDistance** or the **GeoPoint** function.

## Remarks

The **GetPlaceCode** function returns a seven-digit string value containing the Census place code for the submitted location.

ZIP Code boundaries sometime overlap with city limits and unincorporated areas. The ZIP Code may place a location within one city even though it is physically located within a neighboring area. The place code matches the ZIP + 4 code with the Census bureau's official name for that physical location.

If neither the **ComputeDistance** nor the **GeoPoint** function has been called, the submitted data was only a five-digit ZIP Code or if the function call resulted in an error, this function value will return an empty string value.

```
Syntax
```

```
StringValue = object->GetPlaceCode();
C
StringValue = mdGeoGetPlaceCode(object);
COM
StringValue = object.PlaceCode
```

# GetPlaceName

This function returns the Census Bureau place name associated with location passed to either the **ComputeDistance** or the **GeoPoint** function.

## Remarks

The **GetPlaceName** function returns a 60-digit string value containing the Census place name for the submitted location.

ZIP Code boundaries sometime overlap with city limits and unincorporated areas. The ZIP Code may place a location within one city even though it is physically located within a neighboring area. This function returns the Census bureau's official name for the ZIP + 4 code.

#### Chapter 2 GeoCoder Object Functions

For example, the 92688 ZIP Code is located mostly within the city of Rancho Santa Margarita. However, it also contains parts of the unincorporated area of Los Flores. For these ZIP + 4 codes, the **GetCity** function of Address Object would return "Rancho Santa Margarita," but this function will return "Los Flores."

If neither the **ComputeDistance** nor the **GeoPoint** function has been called, the submitted data was only a five-digit ZIP Code or if the function call resulted in an error, this function will return an empty string value.

## **Syntax**

```
StringValue = object->GetPlaceName();
C
StringValue = mdGeoGetPlaceName(object);
COM
StringValue = object.PlaceName
```

# GetTimeZone

This function returns the name of the time zone for the submitted location.

## Remarks

All Melissa Data products express time zones in UTC (Coordinated Universal Time).

This function will return one of the values under the Name column in the following table.

Code	Name	Code	Name
0	Military (APO or FPO)	9	Alaska Time
4	Atlantic Time	10	Hawaii Time
5	Eastern Time	11	Samoa Time
6	Central Time	13	Marshall Islands Time
7	Mountain Time	14	Guam Time
8	Pacific Time	15	Palau Time

The values under the Code column are returned by the **GetTimeZoneCode** function.

Syntax
StringValue = object->GetTimeZone();
C
StringValue = mdGeoGetTimeZone(object);
COM
StringValue = object.TimeZone

# GetTimeZoneCode

This function returns a numeric code for the time zone for the submitted location.

#### Remarks

For a list of the possible values returned by this function, see the table on page 38.

```
Syntax
```

```
StringValue = object->GetTimeZoneCode();
```

#### С

StringValue = mdGeoGetTimeZoneCode(object);

#### СОМ

```
StringValue = object.TimeZoneCode
```

# License Agreement

1. NOTICE. MELISSA DATA CORPORATION IS WILLING TO LICENSE THE ENCLOSED SOFTWARE TO YOU, ONLY ON THE CONDITION THAT YOU ACCEPT ALL OF THE TERMS CONTAINED IN THIS LICENSE AGREEMENT. PLEASE READ THIS LICENSE AGREEMENT CAREFULLY BEFORE OPENING THE SEALED DISK PACKAGE. BY OPENING THIS PACKAGE (OR IN THE CASE OF DOWNLOADED SOFTWARE, YOU REQUEST UNLOCKING CODE FROM THE PUBLISHER) YOU AGREE TO BE BOUND BY THE TERMS OF THIS AGREEMENT. IF YOU DO NOT AGREE TO THESE TERMS WE ARE UNWILLING TO LICENSE THE SOFTWARE TO YOU, AND YOU SHOULD NOT OPEN THE DISK PACKAGE. IN SUCH CASE, PROMPTLY RETURN THE UNOPENED DISK PACKAGE AND ALL OTHER MATERIAL IN THIS PACKAGE ALONG WITH PROOF OF PAYMENT, TO THE AUTHORIZED DEALER FROM WHOM YOU OBTAINED IT FOR A FULL REFUND OF THE PRICE YOU PAID.

**2. Ownership and License.** This is a license agreement and NOT an agreement for sale. We continue to own the copy of the Software (including, but not limited to, object code, dynamic link libraries, and sample programs, together with the accompanying documentation contained in this package and all other copies that you are authorized by this Agreement to make collectively known as "Software"). Your rights to use the Software are specified in this Agreement, and we retain all rights not expressly granted to you in this Agreement. This Software is protected by U.S. copyright laws and

international treaties. Nothing in this Agreement constitutes a waiver of our rights under U.S. Copyright law or any other federal or state law or international treaty.

3. Permitted Uses. You are granted the following rights to the Software:

(a) Right to Install and Use.

(1) Standalone Computer - Single Installation You may install and use the Software on the hard disk drive of any single compatible computer that you own. However, you may not under any circumstances have the Software installed onto the hard drives of two or more computers at the same time, (nor may you install the Software onto the hard disk drive of one computer and then use the original CD-ROM on another computer). If you wish to use the Software on more than one computer, you must either erase the Software from the first hard drive before you install it onto a second hard drive, or else license an additional copy of the Software for each additional computer on which you want to use it.

(2) Network Use: If the single computer on which you install the Software is a network or Internet server, you may use the Software on any computer attached to the network, provided that it is only installed on the server. You may install and use this Software on a single file server regardless of the number of workstations attached to the network.

(b) Right to Copy. You may copy the Software for backup and archival purposes, provided that the original and each copy is kept in your possession, and that your installation and use of the Software does not exceed that allowed in part (a) above.

(1) Solely with the respect to the manual and Help files, you may make an unlimited number of copies (either in hard-copy or electronic form), provided that such copies shall be used only for internal purposes and are not republished or distributed beyond the licensee's premises.

(2) Copy, bundle, or redistribute the DEMO software with any commercial product (including books, CD-ROM, computer hardware, or software products). Your promotional and/or packaging materials must clearly disclose that the Software is copyrighted software of

Melissa Data, that no charge is made by Melissa Data or you for it, and that it is not a fully supported commercial version.

(c) Right to Modify. You may modify the Software and/or merge it into another computer program to the extent necessary for your own use on (a single computer or server as specified above); however, any portion of the Software merged into another computer program will continue to be subject to the terms of this Agreement. You may use and modify the source code version of those Software portions that the documentation identifies as sample code ("SAMPLE CODE"), provided you do not distribute the SAMPLE CODE or any modified version of the SAMPLE CODE, in source form.

(d) Right to Transfer. You may not rent, lend, or lease this Software. However, you may transfer this license to use the Software to another party on a permanent basis by transferring this copy of the License Agreement, at least one unaltered copy of the Software, and all documentation. You must, at the same time, either transfer to the other party or destroy all your other copies of the Software or destroy all of your copies. Such transfer of possession terminates your license from us. Such other party shall be licensed under the terms of this Agreement upon its acceptance of this Agreement by its initial use of the Software. If you transfer the Software, you must remove the Software from your hard disk and you may not retain any copies of the Software for your own use.

4. Prohibited Uses. You may not, without written permission from us:

(a) Use, copy, modify, merge, or transfer copies of the Software or documentation except as provided in this Agreement;

(b) Use any backup or archival copies of the Software (or allow someone else to use such copies) for any purpose other than to replace the original copy in the event it is destroyed or becomes defective;

(c) Disassemble, decompile or reverse engineer, or in any manner decode the Software for any reason;

(d) Distribute, Sublicense, lease, or rent the Software, Data files and/or Dynamic Link Libraries of the Software.

(e) Expose the interfaces of the Software through your application (e.g. an OCX, DLL, class library, etc.).

**5. Limited Warranty.** We make the following limited warranties, for a period of 180 days from the date you acquired the Software from us.

(a) Media. The disks and documentation in this package will be free from defects in materials and workmanship under normal use. If the disks or documentation fail

to conform to this warranty, you may, as your sole and exclusive remedy, obtain a replacement free of charge if you return the defective disk or documentation to us with a dated proof of purchase.

(b) Software. The Software in this package will materially conform to the documentation that accompanies it. If the Software fails to operate in accordance with this warranty, you may, as your sole and exclusive remedy, return all of the Software and the documentation to the authorized dealer from whom you acquired it, along with a dated proof of purchase, specifying the problem, and we will provide you with a new version of the Software or a full refund at our election.

(c) WARRANTY DISCLAIMER. WE DO NOT WARRANT THAT THIS SOFTWARE WILL MEET YOUR REQUIREMENTS OR THAT ITS OPERATION WILL BE UNINTERRUPTED OR ERROR-FREE. WE EXCLUDE AND EXPRESSLY DISCLAIM ALL EXPRESS AND IMPLIED WARRANTIES NOT STATED HEREIN, INCLUDING THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE.

**6. Termination.** This license and your right to use this Software automatically terminate if you fail to comply with any provisions of this Agreement, destroy the copies of the Software in your possession, or voluntarily return the Software to us. Upon termination you will destroy all copies of the Software and documentation. Otherwise, the restrictions on your rights to use the Software will expire upon expiration of the copyright to the Software.

**7. Miscellaneous Provisions.** This Agreement will be governed by and construed in accordance with the substantive laws of California. This is the entire agreement between us relating to the contents of this package, and supersedes any prior purchase order, communications, advertising or representations concerning the contents of this package. No change or modification of this Agreement will be valid unless it is in writing, and is signed by us.